# 配置本地化ISE安装

目录

简介
先决条件
要求
使用的组件
背景信息
了影子信息
配置
步骤1:下载ISO
第二步:配置存储库
第三步:复制ISO
第二步:重新安装软件
第五步:完成安装
验证
拉障排除
相关信息

## 简介

本文档介绍如何配置本地化的身份服务引擎(ISE)安装以重新安装或升级ISE。

## 先决条件

要求

Cisco 建议您了解以下主题:

- 思科ISE 3.X
- 虚拟机
- 安全网络服务器(SNS)设备

使用的组件

- 身份服务引擎(ISE) 3.2补丁5
- 安全传输协议(FTP)服务器

本文档中的信息都是基于特定实验室环境中的设备编写的。本文档中使用的所有设备最初均采用原 始(默认)配置。如果您的网络处于活动状态,请确保您了解所有命令的潜在影响。

## 背景信息

ISE可以作为虚拟机(VM)或在SNS服务器上运行。由于问题或升级过程,有时需要重新安装ISE。在 某些情况下,重新安装ISE会成为一项挑战。因此,ISE 3.2补丁5引入了一项新功能,允许用户使用 命令行重新安装ISE,从而节省大约40分钟。

该功能是本地化ISE安装。在命令行中运行application configure ise命令,显示以下新选项:

• [36]本地化ISE安装。

这意味着要使用此功能,需要安装并运行ISE。

此功能的另一个用途是可以使用它安装更高版本。将此视为升级选项,只需记住,在重新安装 ISE时,此操作会删除所有配置,甚至包括运行配置。



警告:您可以使用此选项重新安装当前版本和更高版本。无法安装低于当前版本的版本。

### 步骤1:下载ISO

1. 导航到<u>下载</u>页面中的ISE文件夹,下载正确的ISO。

1.1.如果要重新安装ISE,请下载相同版本。

1.2.如果要升级,请下载要升级的ISO。

2. 将ISO复制到SFTP服务器。

### 第二步:配置存储库

1. 登录到ISE命令行。

2. 运行以下命令:

#### <#root>

```
#
```

configure terminal

Entering configuration mode terminal #

repository iso

#### #

url sftp://10.10.10.10/folder

% Warning: Repositories configured from CLI cannot be used from the ISE web UI and are not replicated to If this repository is not created in the ISE web UI, it will be deleted when ISE services restart. #

user cisco password plain cisco

#

exit

#### #

exit

#

crypto host\_key add host 10.10.10.10



注意:本示例使用IP地址为10.10.10.10且路径为/folder的SFTP存储库。相应地替换这些值。

### 第三步:复制ISO

1. 将ISO复制到磁盘,运行命令:

<#root>

#

copy repository iso file ise-3.2.0.542.SPA.x86\_64.iso disk://

2. 验证ISO在磁盘中,运行命令:

<#root>

#

```
dir
```

Directory of disk:/ Apr 09 2024 11:01:15 ise-3.2.0.542.SPA.x86\_64.iso

### 第四步:重新安装软件

1. 运行application configure ise命令并键入选项36。

2. 选择ISO。

3. 验证MD5值。您可以获取此值,并将其与<u>下载</u>页面进行比较。

4. 如果MD5值正确,则继续安装。

<#root>

#

application configure ise

Selection configuration option [1]Reset M&T Session Database [2]Rebuild M&T Unusable Indexes [3] Purge M&T Operational Data [4]Reset M&T Database [5]Refresh Database Statistics [6]Display Profiler Statistics [7]Export Internal CA Store [8] Import Internal CA Store [9]Create Missing Config Indexes [10]Create Missing M&T Indexes [12]Generate Daily KPM Stats [13]Generate KPM Stats for last 8 Weeks [14]Enable/Disable Counter Attribute Collection [15]View Admin Users [16]Get all Endpoints [19]Establish Trust with controller [20]Reset Context Visibility [21]Synchronize Context Visibility With Database [22]Generate Heap Dump [23]Generate Thread Dump [24] Force Backup Cancellation [25]CleanUp ESR 5921 IOS Crash Info Files [26]Recreate undotablespace [27]Reset Upgrade Tables [28]Recreate Temp tablespace [29]Clear Sysaux tablespace [30] Fetch SGA/PGA Memory usage

[31]Generate Self-Signed Admin Certificate
[32]View Certificates in NSSDB or CA\_NSSDB
[33]Enable/Disable/Current\_status of RSA\_PSS signature for EAP-TLS
[34]Check and Repair Filesystem
[35]Enable/Disable/Current\_status of Audit-Session-ID Uniqueness
[36]Localised ISE Install
[0]Exit

36

ISO files present in the disk are:

[1] ise-3.2.0.542.SPA.x86\_64.iso

[2] ise-3.1.0.518b.SPA.x86\_64.iso

Choose the ISO you want to install:

1

Computing MD5 hash value of the selected ISO... File selected:ise-3.2.0.542.SPA.x86\_64.iso (MD5:

2e609b6cbeaa5c360d0a09a2a5d3c564

)

Warning: Verify the MD5 checksum of the ISO before you proceed. Proceed with Installation? [y/n]

У

Copying ISO contents to installer directories. The copy may take around 5 minutes. % Notice: The appliance will reboot to install the chosen Cisco ISE release now.



注意:请勿在本示例中使用MD5值,因为ISO文件可以更改,即使它表示它适用于ISE 3.2。

始终在<u>下载</u>中验证它。

5. 检查控制台以监控安装。

_		
r	ne.	Stopping udeo Kernel Device Manager
r.	OR .	1 Stonned Load Kernel Modules
		Stonning Open-iSCSI
r	<b>OK</b>	1 Stonned target Slices.
ř.	ПK	1 Started Setup Victual Console.
ī.	OK.	1 Started Plumouth switch root service.
Ľ.	ΟK	1 Stopped Open-iSCS1.
E.	ŨК	1 Started Cleaning Up and Shutting Down Daemons.
		Stopping iSCS1 UserSpace L/O driver
Ľ	ŨК	1 Closed Open-iSCS1 isosid Socket.
Ľ	ΩK	1 Stopped iSCSI UserSpace L/O driver.
Ľ	QК	1 Closed Open-iSCS1 iscsinio Socket.
I,	OК	1 Stopped udev Kernel Device Manager.
I.	QΚ	] Stopped Create Static Device Nodes in /dev.
I.	QК	1 Stopped Create list of required static device nodes for the current kernel.
		Stopping Hardware RMG Entropy Gatherer Daemon
1	QК	1 Stopped dracut pre-udev hook.
5	OK	1 Stopped dracut endline hook.
	UK	J Closed udev Kernel Socket.
L	ШĶ	J Closed udev Control Socket.
		Starting Cleanup udewd DU
ţ.	UK	J Stopped Hardware NMS Entropy Gatherer Daemon.
ļ.	UK	J Started Cleanup udeva DB.
	uк	J Reached target Switch Noot.
	4.5	0424001 uninth: sustand: 20 output lines summared due to untalimiting
ř	1946 1946	2922241 SPLinux: malicu conskilitu network neer contrals:1
i.	1.4	2872191 SElimori malicu canakilitu onen neresit
î	14	.7881101 SELinux: policy capability extended socket class=1
ĩ	14	2884481 SELinux: policy capability always check network=0
ĩ	14	2882321 SELinux: policy capability corroup seclabel=1
Ē.	14	2890461 SELinux: policy capability map nosuid transition=1
ī.	14	.0222261 audit: tupe=1403 audit(1712593761.934:2): auid=4294967295 ses=4294967295 lsn=selinux
re:	s=1	
Ú	14	.8241931 systemd[1]: Successfully loaded SELinux policy in 346.300ms.

正在安装

### 第五步:完成安装

1. 一旦安装完成,就应该执行运行配置。键入setup。



设置菜单

## 验证

安装ISE后,验证版本和服务。

1. 运行命令show version。

<#root>

#

show version

Cisco Application Deployment Engine OS Release: 3.2 ADE-OS Build Version: 3.2.0.542 ADE-OS System Architecture: x86\_64

Copyright (c) 2005-2022 by Cisco Systems, Inc. All rights reserved. Hostname: asc-ise32-726

Version information of installed applications

3.2.0.542

Build Date : Tue Aug 30 12:21:58 2022 Install Date : Tue Apr 9 09:25:41 2024

2. 运行show application status ise命令以检查您的服务正在运行。

3. 登录图形界面。

## 故障排除

1. 配置存储库后,验证它是否有效。运行命令show repository iso。

2. 验证MD5值。

3. 如果使用的是较低版本,则会出现下一个错误:

Error: You cannot install an earlier version of Cisco ISE (3.1.0). The minimum supported version for in

## 相关信息

•思科技术支持和下载

### 关于此翻译

思科采用人工翻译与机器翻译相结合的方式将此文档翻译成不同语言,希望全球的用户都能通过各 自的语言得到支持性的内容。

请注意:即使是最好的机器翻译,其准确度也不及专业翻译人员的水平。

Cisco Systems, Inc. 对于翻译的准确性不承担任何责任,并建议您总是参考英文原始文档(已提供 链接)。