

如何將我的思科郵件安全裝置(ESA)上的傳輸速率限制為特定域或主機？

目錄

[簡介](#)

[解決方案](#)

簡介

本文檔介紹如何對特定域或主機的傳送進行速率限制。

解決方案

CLI上的 *destconfig* 命令或GUI中 *Mail Policies* 頁籤上的 *Destination Controls* 表可用於在思科郵件安全裝置上配置特定域或主機的傳送速率限制。有時建議啟用此選項以防止載入遠端主機。

以下是如何將速率傳遞限制到域「example.com」的CLI示例。

```
mail.example.com> destconfig
There are currently 2 entries configured.
Choose the operation you want to perform:
- NEW - Create a new entry.
- EDIT - Modify an entry.
- DELETE - Remove an entry.
- DEFAULT - Change the default.
- PRINT - Display all entries.
- CLEAR - Remove all entries.
[ ]> new
Enter the domain you wish to limit.
[ ]> example.com
Do you wish to configure a concurrency limit for example.com? [Y]>
Enter the max concurrency limit for "example.com".
[500]> 100
Do you wish to apply a recipient limit to this domain? [N]> y
Enter the number of minutes used to measure the recipient limit.
[60]> 60
Enter the max number of recipients per 60 minutes for "example.com".
[ ]> 1000
Select how you want to apply the limits for example.com:
1. One limit applies to the entire domain example.com
2. Separate limit for each mail exchanger IP address
[1]>
Select how the limits will be enforced:
1. System Wide
2. Per Virtual Gateway(tm)
```

[1]>

Do you wish to apply a specific TLS setting for this domain? [N]>

Do you wish to apply a specific bounce verification address tagging setting for this domain?
[N]>

Do you wish to apply a specific bounce profile to this domain? [N]>

There are currently 3 entries configured

Choose the operation you want to perform:

- NEW - Create a new entry.
- EDIT - Modify an entry.
- DELETE - Remove an entry.
- DEFAULT - Change the default.
- PRINT - Display all entries.
- CLEAR - Remove all entries.

[]>

mail.example.com> commit