زاهج نم تانايبلا ةدعاقل يطايتحالا خسنلا رخآ ىلا Cisco M-Series قلسلسلا نم

تايوتحملا

<u>قمدق مل </u> <u>قيساسأل اتابلطتمل اتابلطتمل اتابلطتمل اتابلطتمل التابلطة ملك مل التابلطة من التابلطة التا</u>

ةمدقملا

قلسلسلا نم زاهج نم (DB) تانايبلا ةدعاقل يطايتحالا خسنلا ةيفيك دنتسملا اذه حضوي Cisco M-Series رخآ يل

ةيساسألا تابلطتملا

تابلطتملا

:ةيلاتلا عيضاوملاب ةفرعم كيدل نوكت نأب Cisco يصوت

ثدحألا تارادصإلاو AsyncOS 7.2

ة لكشملا

.M ةئفلا نم يوناث زاهج ىلإ DB ل يطايتحالا خسنلا ءدب

لحلا

نم يوناث زاهج ىل تانايبلا قدعاقل يطايتحالا خسنلا عدب لبق تابلطتملا يلي اميف M.

- رادصإلا) AsyncOS رادصإ سفن ىلع M ةئفلا نم نيزاهجلا الك نوكي نأ بجي AsyncOS (رادصإلا)
- خسنلل صرقلا ىلع ةيفاك ةحاسم ىلع M ةئفلا نم فدهلا زاهجلا يوتحي نأ بجي اللهجي اللهجي اللهجي في البحي اللهجي الم لوح تنرتنال اللهجي قئاثولا رظنا) **صارقال قراد اللهجي المنال المنال اللهجيب اللهجيب اللهجيب اللهجيب اللهجيب المناط المناط**

ةلثامم ةلاسر ىلع لصحت دقف ،دادعإلا ءانثأ صرقلا ىلع ةيفاك ةحاسم كيدل نكت مل اذإ ذهل: allocation for these services on the target machine.

وأ

Verifying target machine for version compatibility and disk space...

Backup cannot be scheduled. Reason: There is not enough space for Centralized
Web Tracking. Please increase disk allocation for these services on the target
machine.

.فدەلا زاەجلا ىلع اقبسم روكذم وە امك صرقلل ةېبسنلا ةصحلا نم ققحت

خسنلا) فدهلا M1050 و ،(**m650sma.run** مساب DB ماظن ردصم) M650 و ،(SMA) و ،(MA) عامألا قرادا ازاهج DB مساب DB و ،(P 192.168.15.1).

رماوألا لخدأو (sma1.example.com انرابتخإ يف) M-Series رماوألا لخدأو (sma1.example.com انرابتخإ يف) عن الله تقال الجس

smal.example.com> backupconfig Choose the operation you want to perform: - VIEW - View scheduled backups - VERIFY - Verify if backup can be scheduled to a remote machine - SCHEDULE - Schedule backup to an appliance - CANCEL - Cancel a scheduled backup - STATUS - Show the status of a backup in progress. - SETUP - Configure backup parameters. []> setup Enter level of verbosity: < this can be 0 or 3 0=lowest verbosity of backup logs and 3 is the highest> 0 < 101Compression is desirable on slow connections, but will only slow down backup on fast networks. Would you like to enable compression? [N]> <hit enter here to pick default withing the brackets [N]> Choose the operation you want to perform: - VIEW - View scheduled backups - VERIFY - Verify if backup can be scheduled to a remote machine - SCHEDULE - Schedule backup to an appliance - CANCEL - Cancel a scheduled backup

[]> 192.168.15.1

Enter a name to identify this appliance
[]>sma2.example.com

- STATUS - Show the status of a backup in progress.

Enter the IP address of a machine to transfer data to.

Please enter username and password: Username:

- SETUP - Configure backup parameters.

[] > admin

[]> verify

```
Password:
[]> <enter admin password for the target SMA>
Verifying target machine for version compatibility and disk space...
Backup can be scheduled on to 192.168.15.1.
Choose the operation you want to perform:
- VIEW - View scheduled backups
- VERIFY - Verify if backup can be scheduled to a remote machine
- SCHEDULE - Schedule backup to an appliance
- CANCEL - Cancel a scheduled backup
- STATUS - Show the status of a backup in progress.
- SETUP - Configure backup parameters.
[]> schedule
Enter the IP address of a machine to transfer data to.
[]> 192.168.15.1
Enter a name to identify this appliance
[]>sma2.example.com
Please enter username and password:
Username:
[] > admin
Password:
[]> <type the admin password on the target SMA>
Verifying target machine for version compatibility and disk space...
1. Set up a repeating backup schedule
2. Schedule a single backup
3. Start a single backup now
[1]>
1. Daily
2. Weekly
3. Monthly
[1] > 3
What day of the month would you like the backup to occur?
[1]> <hit enter here>
What time of day would you like the backup to start? Please enter in HH:MM
format.
[]> 02:00
Please enter a name for this backup job:
[]> weekly
Backup "weekly" has been scheduled successfully.
Choose the operation you want to perform:
- VIEW - View scheduled backups
- VERIFY - Verify if backup can be scheduled to a remote machine
- SCHEDULE - Schedule backup to an appliance
- CANCEL - Cancel a scheduled backup
- STATUS - Show the status of a backup in progress.
- SETUP - Configure backup parameters.
[]> view
Scheduled Backups:
# Name IP
                       Schedule
_ _____
1 weekly To 192.168.15.1 on day 1 of every month at 02:00
```

Choose the operation you want to perform:

- VIEW View scheduled backups
- VERIFY Verify if backup can be scheduled to a remote machine
- SCHEDULE Schedule backup to an appliance
- CANCEL Cancel a scheduled backup
- STATUS Show the status of a backup in progress.
- SETUP Configure backup parameters.
- []> <hit enter until your back in CLI>

sma1.example.com> commit

Please enter some comments describing your changes: []> scheduled a weekly backup

Changes committed: Wed Mar 16 18:09:51 2011 GMT smal.example.com>

ةمجرتلا هذه لوح

تمهرت Cisco تا الرمستنع باستغام مهووة من التقن وات الآلية تالولية والرسبين في همود أنعاء الوالم والربشبين في هميد أنعاء الوالم والربشبين في هميو أنعاء الوالم والمتابين في المعالفة أن أفضل تمهرت أن تفون عقوقة طما وتام الفات وتواد المعالفية أن أفضل تمهرت التوالية التولية المالية المالية