

# PIX/ASA 7.x ou posterior: Exemplo de configuração de VPN IPsec LAN a LAN com redes sobrepostas

## Contents

[Introduction](#)  
[Prerequisites](#)  
[Requirements](#)  
[Componentes Utilizados](#)  
[Produtos Relacionados](#)  
[Conventions](#)  
[Configurar](#)  
[Diagrama de Rede](#)  
[Configurações](#)  
[Verificar](#)  
[Comandos show do ASA-1](#)  
[Comandos show do ASA-2](#)  
[Troubleshoot](#)  
[Cancele associações de segurança](#)  
[Comandos para Troubleshooting](#)  
[Informações Relacionadas](#)

## [Introduction](#)

Este documento descreve as etapas usadas para traduzir (NAT) o tráfego VPN que viaja por um túnel de IPsec de LAN a LAN (L2L) entre dois mecanismos de segurança e também PAT de tráfego da Internet. Cada dispositivo de segurança tem uma rede privada protegida por trás dela. Neste exemplo, dois Cisco Adaptive Security Appliances (ASAs) com redes internas idênticas e sobrepostas são conectadas pelo túnel VPN. Em um cenário normal, a comunicação através da VPN nunca acontece porque os pacotes de ping nunca deixam a sub-rede local desde que o usuário faça ping no endereço IP da mesma sub-rede. Para que essas duas redes internas privadas se comuniquem entre si, o NAT de política é usado em ambos os ASAs para tradução da sub-rede local, de modo que a comunicação ocorra conforme esperado.

## [Prerequisites](#)

## [Requirements](#)

Certifique-se de ter configurado o Cisco Adaptive Security Appliance com endereços IP nas interfaces e ter conectividade básica antes de prosseguir com este exemplo de configuração.

## Componentes Utilizados

As informações aqui são baseadas nesta versão de software:

- Cisco Adaptive Security Appliance Software versão 7.x e posterior.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

## Produtos Relacionados

Essa configuração também pode ser usada com o Cisco PIX Security Appliance versão 7.x ou posterior.

## Conventions

Consulte as [Convenções de Dicas Técnicas da Cisco para obter mais informações sobre convenções de documentos.](#)


## Configurar

Nesta seção, você encontrará informações para configurar os recursos descritos neste documento.

Nota: Use a Command Lookup Tool (somente clientes registrados) para obter mais informações sobre os comandos usados nesta seção.

## Diagrama de Rede

Este documento utiliza a seguinte configuração de rede:



## Configurações

Este documento utiliza as seguintes configurações:

- [Configuração do ASA-1](#)
- [Configuração do ASA-2](#)

## ASA-1

```
ASA-1#show running-config
:
:
ASA Version 8.0(3)
!
hostname ciscoasa
enable password 8Ry2YjIyt7RRXU24 encrypted
names
!
interface Ethernet0
 nameif outside
 security-level 0
 ip address 172.162.1.1 255.255.255.0
!--- Configure the outside interface. ! interface
Ethernet1 nameif inside security-level 100 ip address
192.168.1.1 255.255.255.0 !--- Configure the inside
interface. passwd 2KFQnbNIIdI.2KYOU encrypted ftp mode
passive access-list new extended permit ip 192.168.2.0
255.255.255.0 192.168.3.0 255.255.255.0 !--- This access
list (new) is used with the crypto map (outside_map) !--
- in order to determine which traffic should be
encrypted !--- and sent across the tunnel.
access-list policy-nat extended permit ip 192.168.1.0
255.255.255.0 192.168.3.0 255.255.255.0

!--- The policy-nat ACL is used with the static !---
command in order to match the VPN traffic for
translation.

pager lines 24
mtu outside 1500
mtu inside 1500
no failover
asdm image flash:/asdm-615.bin
no asdm history enable
arp timeout 14400

static (inside,outside) 192.168.2.0 access-list policy-
nat
!--- It is a Policy NAT statement. !--- The static
command with the access list (policy-nat), !--- which
matches the VPN traffic and translates the source
(192.168.1.0) to !--- 192.168.2.0 for outbound VPN
traffic.

global (outside) 1 interface
nat (inside) 1 0.0.0.0 0.0.0.0 0 0
!--- The previous statements PAT the Internet traffic !-
-- except for the VPN traffic that uses the IP address
172.17.1.1. route outside 0.0.0.0 0.0.0.0 172.162.1.2 1
!--- Output is suppressed. !--- PHASE 2 CONFIGURATION --
-! !--- The encryption types for Phase 2 are defined
here. crypto ipsec transform-set CISCO esp-des esp-md5-
hmac !--- Define the transform set for Phase 2. crypto
map outside_map 20 match address new !--- Define which
traffic should be sent to the IPsec peer with the !---
access list (new). crypto map outside_map 20 set peer
172.162.1.2 !--- Sets the IPsec peer (remote end point)
crypto map outside_map 20 set transform-set CISCO !---
```

```

Sets the IPsec transform set "CISCO" !--- to be used
with the crypto map entry "outside_map" crypto map
outside_map interface outside !--- Specifies the
interface to be used with !--- the settings defined in
this configuration !--- PHASE 1 CONFIGURATION ---! !---
This configuration uses isakmp policy 65535. !--- Policy
65535 is included in the configuration by default. !---
These configuration commands define the !--- Phase 1
policy parameters that are used. crypto isakmp identity
address crypto isakmp enable outside crypto isakmp
policy 65535 authentication pre-share encryption des
hash md5 group 2 lifetime 86400 tunnel-group 172.162.1.2
type ipsec-l2l !--- In order to create and manage the
database of connection-specific records !--- for IPsec-
L2L-IPsec (LAN-to-LAN) tunnels, use the tunnel-group !--
- command in global configuration mode. !--- For L2L
connections, the name of the tunnel group must be !---
the IP address of the IPsec peer (remote peer end).

tunnel-group 172.162.1.2 ipsec-attributes
  pre-shared-key *
!--- Enter the pre-shared key in order to configure the
authentication method. telnet timeout 5 ssh timeout 5
console timeout 0 ! class-map inspection_default match
default-inspection-traffic ! ! policy-map global_policy
class inspection_default inspect dns maximum-length 512
inspect ftp inspect h323 h225 inspect h323 ras inspect
netbios inspect rsh inspect rtsp inspect skinny inspect
esmtp inspect sqlnet inspect sunrpc inspect tftp inspect
sip inspect xdmcp ! service-policy global_policy global
Cryptochecksum:33e1e37cd1280d908210dac0cc26e706 : end

```

## ASA-2

```

ASA-2#show running-config
: Saved
:
ASA Version 8.0(3)
!
hostname ASA-2
enable password 8Ry2YjIyt7RRXU24 encrypted
names
!
interface Ethernet0
  nameif outside
  security-level 0
  ip address 172.162.1.2 255.255.255.0
!
interface Ethernet1
  nameif inside
  security-level 100
  ip address 192.168.1.1 255.255.255.0
!
!--- Output is suppressed. access-list new extended
permit ip 192.168.3.0 255.255.255.0 192.168.2.0
255.255.255.0 !--- This access list (new) is used with
the crypto map (outside_map) !--- in order to determine
which traffic needs to be encrypted !--- and sent across
the tunnel.
access-list policy-nat extended permit ip 192.168.1.0
255.255.255.0 192.168.2.0 255.255.255.0
!--- The policy-nat ACL is used with the static !---

```

```
command in order to match the VPN traffic for  
translation.
```

```
pager lines 24  
mtu outside 1500  
mtu inside 1500  
no failover  
asdm image flash:/asdm-615.bin  
no asdm history enable  
arp timeout 14400
```

```
static (inside,outside) 192.168.3.0 access-list policy-  
nat
```

```
!--- This is a Policy NAT statement. !--- The static  
command with the access list (policy-nat), !--- which  
matches the VPN traffic and translates the source  
(192.168.1.0) to !--- 192.168.3.0 for outbound VPN  
traffic.
```

```
global (outside) 1 interface  
nat (inside) 1 0.0.0.0 0.0.0.0 0 0  
!--- The previous statements PAT the Internet traffic !-  
-- except the VPN traffic that uses the outside  
interface IP address. route outside 0.0.0.0 0.0.0.0  
172.162.1.2 1 !--- PHASE 2 CONFIGURATION ---! !--- The  
encryption types for Phase 2 are defined here. crypto  
ipsec transform-set CISCO esp-des esp-md5-hmac !---  
Define the transform set for Phase 2. crypto map  
outside_map 20 match address new !--- Define which  
traffic needs to be sent to the IPsec peer. crypto map  
outside_map 20 set peer 172.162.1.1 !--- Sets the IPsec  
peer. crypto map outside_map 20 set transform-set CISCO  
!--- Sets the IPsec transform set "CISCO" !--- to be  
used with the crypto map entry "outside_map". crypto map  
outside_map interface outside !--- Specifies the  
interface to be used with !--- the settings defined in  
this configuration. !--- PHASE 1 CONFIGURATION ---! !---  
This configuration uses isakmp policy 65535 !--- which  
is included in the configuration by default. !--- The  
configuration commands here define the !--- Phase 1  
policy parameters that are used. crypto isakmp identity  
address crypto isakmp enable outside crypto isakmp  
policy 65535 authentication pre-share encryption des  
hash md5 group 2 lifetime 86400 !--- Output is  
suppressed. !--- In order to create and manage the  
database of connection-specific !--- records for IPsec-  
L2L-IPsec (LAN-to-LAN) tunnels, use the !--- tunnel-  
group command in global configuration mode. !--- For  
L2L connections, the name of the tunnel group must be !-  
-- the IP address of the IPsec peer.
```

```
tunnel-group 172.162.1.1 type ipsec-l2l  
tunnel-group 172.162.1.1 ipsec-attributes  
pre-shared-key *  
!--- Enter the pre-shared key in order to configure the  
authentication method. prompt hostname context  
Cryptochecksum:6b505b4a05c1aee96a71e67c23e71865 : end
```

[Verificar](#)

Use esta seção para confirmar se a sua configuração funciona corretamente.

A [Output Interpreter Tool \(somente clientes registrados\) \(OIT\)](#) oferece suporte a determinados comandos show. Use a OIT para visualizar uma análise da saída do comando show:

- **show crypto isakmp sa** – Mostra todas as associações de segurança (SAs) IKE atuais no correspondente.
- **show crypto ipsec sa** - Mostra as configurações usadas pelas SAs atuais.

## [Comandos show do ASA-1](#)

```
ASA-1#show crypto isakmp sa
```

```
Active SA: 1
    Rekey SA: 0 (A tunnel will report 1 Active and 1 Rekey SA during rekey)
Total IKE SA: 1

1   IKE Peer: 172.162.1.2
    Type      : L2L           Role     : initiator
    Rekey     : no            State    : MM_ACTIVE
```

```
ASA-1#show crypto ipsec sa
```

```
interface: outside
    Crypto map tag: outside_map, seq num: 20, local addr: 172.162.1.1

        access-list new permit ip 192.168.2.0 255.255.255.0 192.168.3.0
        255.255.2
        5.0
            local ident (addr/mask/prot/port): (192.168.2.0/255.255.255.0/0/0)
            remote ident (addr/mask/prot/port): (192.168.3.0/255.255.255.0/0/0)
            current_peer: 172.162.1.2

            #pkts encaps: 9, #pkts encrypt: 9, #pkts digest: 9
            #pkts decaps: 9, #pkts decrypt: 9, #pkts verify: 9
            #pkts compressed: 0, #pkts decompressed: 0
            #pkts not compressed: 9, #pkts comp failed: 0, #pkts decomp failed: 0
            #pre-frag successes: 0, #pre-frag failures: 0, #fragments created: 0
            #PMTUs sent: 0, #PMTUs rcvd: 0, #decapsulated frgs needing reassembly: 0
            #send errors: 0, #recv errors: 0

        local crypto endpt.: 172.162.1.1, remote crypto endpt.: 172.162.1.2

        path mtu 1500, ipsec overhead 58, media mtu 1500
        current outbound spi: 0BA6CD7E

    inbound esp sas:
        spi: 0xFB4BD01A (4216049690)
            transform: esp-des esp-md5-hmac none
            in use settings ={L2L, Tunnel, }
            slot: 0, conn_id: 8192, crypto-map: outside_map
            sa timing: remaining key lifetime (kB/sec): (3824999/27738)
            IV size: 8 bytes
            replay detection support: Y
    outbound esp sas:
        spi: 0x0BA6CD7E (195480958)
            transform: esp-des esp-md5-hmac none
```

```

in use settings ={L2L, Tunnel, }
slot: 0, conn_id: 8192, crypto-map: outside_map
sa timing: remaining key lifetime (kB/sec): (3824999/27738)
IV size: 8 bytes
replay detection support: Y

```

ASA-1#**show nat**

```

NAT policies on Interface inside:
match ip inside 192.168.1.0 255.255.255.0 outside 192.168.3.0 255.255.255.0
  static translation to 192.168.2.0
  translate_hits = 12, untranslate_hits = 5
match ip inside any outside any
  dynamic translation to pool 1 (172.162.1.1 [Interface PAT])
  translate_hits = 0, untranslate_hits = 0
match ip inside any inside any
  dynamic translation to pool 1 (No matching global)
  translate_hits = 0, untranslate_hits = 0
match ip inside any dmz any
  dynamic translation to pool 1 (No matching global)
  translate_hits = 0, untranslate_hits = 0

```

ASA-1#**show xlate**

```

1 in use, 1 most used
Global 192.168.2.0 Local 192.168.1.0

```

## Comandos show do ASA-2

ASA-2#**show crypto ipsec sa**

```

interface: outside
  Crypto map tag: outside_map, seq num: 20, local addr: 172.162.1.2
    access-list new permit ip 192.168.3.0 255.255.255.0 192.168.2.0
      255.255.255.255
      5.0
        local ident (addr/mask/prot/port): (192.168.3.0/255.255.255.0/0/0)
        remote ident (addr/mask/prot/port): (192.168.2.0/255.255.255.0/0/0)
        current_peer: 172.162.1.1

        #pkts encaps: 9, #pkts encrypt: 9, #pkts digest: 9
        #pkts decaps: 9, #pkts decrypt: 9, #pkts verify: 9
        #pkts compressed: 0, #pkts decompressed: 0
        #pkts not compressed: 9, #pkts comp failed: 0, #pkts decomp failed: 0
        #pre-frag successes: 0, #pre-frag failures: 0, #fragments created: 0
        #PMTUs sent: 0, #PMTUs rcvd: 0, #decapsulated frgs needing reassembly: 0
        #send errors: 0, #recv errors: 0

  local crypto endpt.: 172.162.1.2, remote crypto endpt.: 172.162.1.1
    path mtu 1500, ipsec overhead 58, media mtu 1500
    current outbound spi: FB4BD01A

  inbound esp sas:
    spi: 0x0BA6CD7E (195480958)
      transform: esp-des esp-md5-hmac none
      in use settings ={L2L, Tunnel, }
      slot: 0, conn_id: 8192, crypto-map: outside_map
      sa timing: remaining key lifetime (kB/sec): (4274999/26902)

```

```

IV size: 8 bytes
replay detection support: Y
outbound esp sas:
    spi: 0xFB4BD01A (4216049690)
        transform: esp-des esp-md5-hmac none
        in use settings ={L2L, Tunnel, }
        slot: 0, conn_id: 8192, crypto-map: outside_map
        sa timing: remaining key lifetime (kB/sec): (4274999/26902)
        IV size: 8 bytes
        replay detection support: Y

```

ASA-2#**show crypto isakmp sa**

```

Active SA: 1
    Rekey SA: 0 (A tunnel will report 1 Active and 1 Rekey SA during rekey)
Total IKE SA: 1

1  IKE Peer: 172.162.1.1
    Type      : L2L          Role      : responder
    Rekey     : no           State    : MM_ACTIVE

```

## [\*\*Troubleshoot\*\*](#)

### [\*\*Cancele associações de segurança\*\*](#)

Ao solucionar problemas, certifique-se de limpar as SAs existentes após fazer uma alteração. No modo privilegiado do PIX, use estes comandos:

- **clear crypto ipsec sa** - Exclui as SAs IPsec ativas.
- **clear crypto isakmp sa** - Exclui as SAs IKE ativas.

### [\*\*Comandos para Troubleshooting\*\*](#)

A [ferramenta Output Interpreter \(exclusiva para clientes registrados\)](#) é compatível com alguns comandos de exibição.. Use a OIT para visualizar uma análise da saída do comando **show**.

Nota: Consulte [Informações Importantes sobre Comandos de Depuração](#) antes de usar comandos debug.

- **debug crypto isakmp** – Exibe as negociações IPSec da Fase 2.
- **debug crypto isakmp** – Exibe as negociações ISAKMP da Fase 1.

## [\*\*Informações Relacionadas\*\*](#)

- [Soluções de problemas mais comuns para VPN IPsec de acesso remoto e L2L](#)
- [PIX 7.0 e Adaptive Security Appliance Port Redirection\(Forwarding\) com comandos nat, global, estático, conduit e access-list](#)
- [PIX/ASA 7.x e FWSM: Declarações de NAT e PAT](#)
- [Ferramentas de segurança do Cisco ASA 5500 Series](#)
- [Cisco PIX 500 Series Security Appliances](#)
- [Negociação IPsec/Protocolos IKE](#)

- [Suporte Técnico e Documentação - Cisco Systems](#)