

# Microsoft Windows で pscp を使用する方法を教えてください。

## 目次

[質問](#)

[環境](#)

[解決策](#)

## 質問

Microsoft Windows で pscp を使用する方法を教えてください。

## 環境

Cisco E メール セキュリティ アプライアンス ( ESA )、Web セキュリティ アプライアンス ( WSA )、セキュリティ管理アプライアンス ( SMA )、AsyncOS のすべてのバージョン

## 解決策

このナレッジ ベース記事では、シスコによる保守およびサポートの対象でないソフトウェアを参照しています。情報は、利便性のために無償で提供されています。さらにサポートが必要な場合は、ソフトウェアベンダーに連絡してください。

<http://www.chiark.greenend.org.uk/~sgtatham/putty/download.html> から pscp.exe をダウンロードして下さい。

ディスクに保存します。

Windows CLI を開きます。[Start] -> [Run] の順に選択し、[Open] フィールドに「command」と入力して [OK] をクリックします。

「pscp.exe」を Windows CLI にドラッグし、CLI にコマンドのフルパスを入力します。

特定のファイルをアップロードします。

```
pscp file user@host: file
```

特定のファイルをダウンロードします。

```
pscp user@host: file file
```

フォルダ内のすべてのファイルをダウンロードします。

```
pscp -unsafe user@host: folder/*.* folder/
```

使用方法 : *pscp [options] [user@]host: source target*

*pscp [options] source [source...] [[user@]host: target*

*pscp [options] -ls [user@]host: filespec*

*Options:*

*--V print version information and exit*

*--pgpfp print PGP key fingerprints and exit*

*--p preserve file attributes*

*--q quiet, don't show statistics*

*--r copy directories recursively*

*--v show verbose messages*

*--load sessname Load settings from saved session*

*--P port connect to specified port*

*--l user connect with specified username*

*--pw passw login with specified password*

*--1 -2 force use of particular SSH protocol version*

*--4 -6 force use of IPv4 or IPv6*

*--C enable compression*

*--i key private key file for authentication*

*--batch disable all interactive prompts*

*--unsafe allow server-side wildcards (DANGEROUS)*

*--sftp force use of SFTP protocol*

*--scp force use of SCP protocol*